



User's Manual for μ Lab 3

revision 1.0

the innovation will play forever
SIMNUMERICA

Contents

1	Getting Started	1
1.1	Register on the web site and activate your muLab account .	3
1.2	Installing an ssh client (putty) and setting the remote connection	4
1.2.1	Linux/Mac users	8
1.3	Install VNC viewer and connect to your remote desktop session	9
1.3.1	Linux/Mac users	13
1.4	Run μ Lab [®]	15
1.5	Copying your files into your μ Lab [®] remote account space .	17
1.5.1	Linux/Mac users	20
1.6	Final touches	21
1.6.1	Change password	21
1.6.2	Change desktop resolution	23
1.7	MPLAB-X [®] issues	24
1.7.1	MPLAB-X IDE [®] project setup	24
1.7.2	Error: Cannot start communication server	25
1.7.3	Warning: muLab-MPLABX plugin detected that[...] .	26
2	Interface Overview	27
2.1	The menu bar	29
2.1.1	File menu	29
2.1.2	Machine menu	31

2.1.3	Debug procedures menu	33
2.1.4	Test sequences menu	34
2.1.5	Simulation menu	35
2.1.6	Help menu	36
2.2	The Tool bar	37
2.3	The Tool bar for the Machine View	37
	Test bench buttons	37
	Machine buttons	37
	Zoom bar	37
2.4	The Tool bar for the Simulation View	38
	Simulation buttons	38
2.5	The main pane	39
2.5.1	Machine view	39
	Graph pane	40
	Info pane	41
2.5.2	Project Dictionaries view	45
2.5.3	Debug Procedures view	46
2.5.4	Test Sequences view	47
2.5.5	Simulations view	47
2.6	The status bar	49
2.6.1	Log Console	49
2.6.2	Status Info	49
2.6.3	Memory Usage icon	50
2.7	Notes and Reports	51
2.7.1	Test Reports	51
2.7.2	Working Notes	52
3	Machine/Process Modelling	53
3.1	Test bench	53
3.1.1	Creating a new test bench	53
3.1.2	Loading an existing test bench	54
3.2	Components	55
3.2.1	Component creation	55
3.2.2	Model type	55
3.2.3	Numerical model	56

3.2.3.1	Default Python model template	57
3.2.3.2	Constant Gain model template	57
3.2.3.3	LaTeX model template	58
3.2.3.4	Thermometer model template	59
3.2.3.5	Voltage Divider model template	59
3.2.3.6	Wave Generator model template	60
3.2.4	Parameters and variables	60
3.2.5	Pins and plugs	61
3.2.6	Post-creation editing	62
3.3	Embedded Platforms	62
3.3.1	Embedded Platform creation	62
3.3.2	Pinout	63
3.3.2.1	Clock frequency	64
3.3.2.2	Input voltage	64
3.3.2.3	Input/Output frequency-modulated pulse train	64
3.3.2.4	Input/Output width-modulated pulse train	64
3.3.2.5	Input/Output bit stream	65
3.3.2.6	Device pin	65
3.3.3	Plugs	65
3.3.4	Post-creation editing	65
3.4	Links	65
3.5	Groups	68
4	Project Dictionaries Design	71
4.1	Dictionary of firmware variables/subroutines	72
4.2	Dictionary of processor I/O signals	72
4.3	Dictionary of processor implementations	73
4.4	Dictionary of runtime firmware subroutines substitutions	74
4.5	Dictionary of firmware implementations	76
4.6	Dictionary of external data files	77
4.7	Dictionary of post-process scripts	77

5	Debug Procedures Design	83
5.1	Creating a Debug Procedure	83
5.2	Renaming a Debug Procedure	83
5.3	Deleting a Debug Procedure	84
5.4	Creating/Editing/Deleting a Debug Instruction	85
5.5	Rearranging the Debug Instruction list	87
6	Test Sequences Design	89
6.1	Creating a new Test Sequence	89
6.2	Renaming a Test Sequence	89
6.3	Deleting a test sequence	90
6.4	Copy/Paste a test sequence	90
6.5	Creating/Editing/Deleting a new Test	91
6.6	Rearranging the Test list	91
7	Co-Simulations run	99
7.1	Starting Simulation	100
7.1.1	Test selection	100
7.1.2	Machine configuration	101
7.1.3	Links configuration	103
7.1.4	Debug components	104
7.2	Simulation flow	105
7.2.1	Pausing Simulations	105
7.2.2	Resuming Simulations	105
7.2.3	Aborting Simulations	105
7.3	Data visualization	106
7.3.1	Data view	106
7.3.2	Chart view	107
7.3.3	Animation view	108
7.3.4	Debug view	109
7.4	Co-simulation logs	111
7.5	Post Processing	112
7.6	Test Reports	113
7.6.1	Reports Manager	113
7.6.2	Text search tools	114

7.6.3	Report Groups management	115
7.7	Working Notes	116

Chapter 1

Getting Started

This chapter describes the preliminary steps you should perform to start using μLab^{\circledR} .

μLab^{\circledR} is meant to be executed as a cloud application, providing the following advantages for its end-users:

- since all the heavy work is being performed in the cloud server, the only system requirement we demand from the developer perspective is a reasonable internet connection; actually, a common standard connection is sufficient to smoothly interact with μLab^{\circledR} ;
- because of this, you don't need to update any of your computer hardware;
- furthermore, because all of your projects run in a cloud server, you can access and work on them from any locations and devices;
- multiple access are allowed, to give to a distributed teamwork the possibility to interact within the same simulation.

Let us describe all the steps needed to get μLab^{\circledR} up and running, as well to provide safety and security to all the data transitioning from your

computer/tablet to the server and viceversa. The current version of this manual assumes by default that you are using the Windows operating system on your client computer, but the same operations can be mad also with other other systems (Linux, Mac), as explained in the *Linux/Mac users* subsection of each section.

1.1 Register on the web site and activate your muLab account

TO DO: UNDER CONSTRUCTION ...

1.2 Installing an ssh client (putty) and setting the remote connection

As mentioned before, data security and safety are of primary concern. Therefore, all communications between your local machine and the server hosting μ Lab[®] should take place through an encrypted SSH connection.

To set up the connection, you first need to download and configure *PuTTY*, freely available [here](#).

Place a shortcut to it in a convenient place, such as in the desktop or taskbar, then launch it. The first option to configure inside PuTTY is the hostname to connect. From the *Category* sidebar, select *Session* subcategory; then, locate the label "*Hostname (or IP address)*" and, in the text field immediately below it, enter the hostname **mulab.simnumerica.com**.

A screenshot of this step is shown in Figure 1.1.




Figure 1.1: Hostname configuration

Please ignore for now the *Session* entries: we will come back later. Now, you need to supply your login credentials to PuTTY, so that it can forward them to the cloud server. To perform this simple operation, just head to the *Connection* -> *Data* subcategory, and locate the *Auto-login username* label. On its right, instead of `your_username` shown in Figure 1.2 as example, insert the username you registered in the *μLab*[®] registration page.




Figure 1.2: Username configuration

At this point, we are almost done with PuTTY configuration: it knows to which server he has to connect, and which username present to it. What it is still missing, is to define how to convey the remote desktop session in the SSH secure channel. In other words, we have to define now a tunnel connection.

To do so, head to the *Connection* -> *Data* -> *SSH* -> *Tunnel* subcategory, and locate the *Source port* and *Destination* input boxes. Recalling the `port_number` you got when you received the activation email response (cfr. sec. 1.1), insert the `port_number` in the *Source port* and, as *Des-*

tion, insert `localhost:port_number`. See example in Figure 1.3, with `port_number` equal to 5906.

Click *Add* to create a tunnelled connection, and you are done. Now, to




Figure 1.3: Tunnel configuration

save your time for every future connection, you can store this session profile and load it when you need it. To do so, head back to *Session* category, below the *Saved Sessions* label type a sensible name for that connection (in Figure 1.1 we saved it as *muLab*), and then click *Save*.

Now you can test your connection: double click on your earlier saved session and a popup will show up, asking to trust our server. You just need to answer *Yes* once: in subsequent connection attempts, that popup will not show again.




Figure 1.4: Server trust request

Once you trusted our server RSA key, the command prompt will show up. Enter your password, the one you choose when you registered in the μ Lab[®] registration page, and you will see a command line prompt pointing at your home directory, located inside the cloud server. See Figure 1.5 as reference.

The command line is not the direct interface you will use in your working session. But, it activates the secure, tunnelled connection that VNC will use to display the remote desktop, which is the interface you will use to interact with μ Lab[®] (see sec. 1.3).




Figure 1.5: Successful connection to the remote server

1.2.1 Linux/Mac users

TO DO: UNDER CONSTRUCTION ...

1.3 Install VNC viewer and connect to your remote desktop session

Now you need to setup the application that will allow you to show the remote desktop and work on it as if you were sitting in front of the cloud server.

For this operation, you have to install *TightVNC*, freely available [here](#). Download and install it as you would do with any other application, just remember not to install *TightVNC Server* because you only need its client application to connect to our server. Therefore, choose the *Cus-*




Figure 1.6: TightVNC installation

tom installation mode as shown in the figure above, and then click on the *TightVNC Server* entry and choose the option *Entire feature will be unavailable*.

At this point, with the PuTTY command line still active, run the *TightVNC Viewer* application: its interface is really minimal, you only have to specify the remote host and your specific port number, and then hit *Connect*




Figure 1.7: TightVNC installation

as shown in Figure 1.8 .



Warning: PuTTY connection **must** be running during the whole VNC session. If you closed it, either accidentally or on purpose, you will lose your remote desktop connection

If everything was setup correctly, now you will be presented a messagebox asking for your password to login into your remote desktop environment.

Enter your password, and you are done! Welcome to your remote desktop environment: you can start using μ Lab[®].




Figure 1.8: VNC configuration




Figure 1.9: VNC authentication




Figure 1.10: VNC remote desktop

For a better view, you can expand the window to fit your screen ... the μ Lab[®] GUI is designed for a full-screen usage. If you wish, you can also set your VNC client to run in fullscreen mode. In case of TightVNC, the shortcut to toggle fullscreen mode on and off is **CTRL+SHIFT+ALT+F**.



Warning: If you think you may forget that shortcut combination, especially after a long session development, you are encouraged to write it down. This is because you won't be able to switch to another application (e.g. to read the PDF of this manual) until you exit the fullscreen mode.


1.3.1 Linux/Mac users

To setup a successful connection to the remote desktop under Linux/Mac, you have to open your favourite terminal application and type, in one single line:

```
ssh -L <port_number>:localhost:<port_number>  
<username>@mulab.simnumerica.com
```

where *<port_number>* must be substituted with your actual port number (the one you received by email) , and *<username>* of course by your username in the remote server.

In the example below, we performed tunnelling of port 5909 for user *Diego*



```
polentino [~]:$ ssh -L 5909:localhost:5909 Diego@mulab.simnumerica.com  
Diego@mulab.simnumerica.com's password:  
Last login: Tue Mar 25 12:05:43 2014 from 10.0.0.100  
[Diego@mulab ~]$
```

Figure 1.11: Linux/Mac tunneling

Now, the steps to connect to your remote desktop are the same shown in Windows: just use your favourite VNC client shipped with your distribution, insert *localhost:<port_number>* as remote local host and click *Connect*: once you provide your remote VNC password, you are done. If, for example, you are using KDE's remote desktop application *KRDC*, simply insert *localhost:<port_number>* and then click the blue arrow on the right, as shown in figure




Figure 1.12: KRDC host specification




Figure 1.13: KRDC config dialog, followed by the password dialog




Figure 1.14: KRDC with remote desktop active on user Diego

1.4 Run $\mu\text{Lab}^{\text{®}}$

From the *Applications* menu, located in the upper left side of the screen, select the *Programming* submenu and launch $\mu\text{Lab}^{\text{®}}$, by clicking the $\mu\text{Lab}^{\text{®}}$ menu entry. After a short time it will appear the $\mu\text{Lab}^{\text{®}}$ login interface, as shown in Figure 1.15: enter your username and password, and start using the $\mu\text{Lab}^{\text{®}}$ environment!




Figure 1.15: $\mu\text{Lab}^{\text{®}}$ login interface

If you want to place a shortcut in the desktop instead, just right click over $\mu\text{Lab}^{\text{®}}$ menu entry and select *Add this launcher to desktop*, as shown in Figure 1.16.

After the program has finished loading, the main $\mu\text{Lab}^{\text{®}}$ dashboard will be shown (see Cap. 2). You can use it to access all of the $\mu\text{Lab}^{\text{®}}$ functions and tools; upon being started, $\mu\text{Lab}^{\text{®}}$ loads by default the *TestBench* used in the last session, restoring graphical properties such as the icon positions on the graph, the size of the main window, ...




Figure 1.16: Run $\mu\text{Lab}^{\text{®}}$ in the remote desktop



Warning:

Once you have completed your $\mu\text{Lab}^{\text{®}}$ session, **do not logout** from your login in the server. If you do so, you won't be able to reconnect with your remote desktop until the server administrator re-activate your login. Instead, just close VNC and PuTTY: once you re-connect again, you will access the same working environment left at the end of your previous session (this can be very useful: for example, if you left a simulation running, you will access to its current status and interact with it).

1.5 Copying your files into your μ Lab[®] remote account space

You have seen how to setup a secure connection, how to display your remote desktop session, and how to launch mulab. The natural step that follows is to start composing one or more *TestBench*, i.e. your virtual prototyping projects within μ Lab[®]: this requires also providing custom firmwares and some Python scripts (to model the physical world interacting with your controller, to perform some postprocess actions, etc.) that may have been written within another computer system.

In principle, you could develop everything from within your remote desktop session but, what you are most likely going to need, is a way to transfer *TestBench* files and simulation datafiles from and to your remote account space. Thus, you need to download and install *WinSCP* from [here](#) (free application).

Its interface is simple and intuitive, as well its setup: once you started it, click on *New* button located in the upper right side of the application, and the interface will change to let you enter details about the session you are going to establish, as you can see in the image below

You only need to fill the following fields:

- *Host name* with `mulab.simnumerica.com`;
- *User name* with `your_username`;
- *Password* with `your_password`, the same used with PuTTY (cfr. sec. 1.2);

After doing so, you can either press the *Login* button or, and we advise you to do so, save this new session and then double click it from the *Stored sessions* list.

If you did type everything correctly, after the connection phase you will see a new window similar to the one shown in Figure 1.18: on the left, you have your local directories and files; on the right, you can explore your remote account directory and subfolders. If you want to upload a file or folder from your local computer to the server, just drag and




Figure 1.17: WinSCP setup page




Figure 1.18: WinSCP connected to mulab remote account space

drop it from the left panel to the right panel. In Figure 1.19 for example, we copied the local folder *mulab* inside

C:\mulab\modules\branches into the remote folder */root/Downloads*. Win-

SCP is smart enough to provide some transfer options to better improve the transfer rate and reduce bandwidth usage: feel free to try them and then press the *Copy* button.




Figure 1.19: WinSCP folder upload to remote server

1.5.1 Linux/Mac users

If you are running any GNU/Linux distribution, you can copy any file and folder with the handy *scp* command. It takes the following parameters:

- the file or folder you need to transfer (when transferring folders, remember to add the *-r* parameter to send the folder and its content, recursively);
- the username in the cloud server, hostname, and destination folder (absolute path) where the file/folder will be placed.

An example of transfer operation of folder *firmware* (empty in that case), executed by user Diego, into his own remote Desktop folder, is shown in the figure below: The first time you perform this operation, *scp* will ask


A terminal window with a menu bar (File, Edit, View, Search, Terminal, Help) and a title bar. The terminal shows the execution of the command 'scp -r firmware/ Diego@mulab.simnumerica.com:/home/Diego/Desktop'. It displays a warning about the host's authenticity, showing the RSA key fingerprint. The user responds 'yes' to continue connecting. A warning message states that the host's fingerprint has been permanently added to the list of known hosts. The terminal then prompts for the password, which is entered as 'diego@mulab.simnumerica.com's password:'. The prompt changes to 'diebian@diebian'.

Figure 1.20: Folder transfer operation using *scp* command

you if you are sure to connect with the host: just reply *yes*, and the server credentials will be saved for the future connections.

TO DO: UNDER CONSTRUCTION ...


1.6 Final touches

Now that you are able to setup a secure connection to the cloud server, copy files and folders into it, and start *μLab*[®], there are some final touches you are likely interested to perform as well.

1.6.1 Change password

For example, you may want to change your login password and your VNC password to something different than the ones you received from the administrator email. This process is really fast and easy to perform, so we highly encourage you to do so.

To change your *user login password*, open a new terminal and type the `passwd` command, as shown in Figure 1.21.

A terminal window titled 'testlogin@localhost:~' with a menu bar (File, Edit, View, Search, Terminal, Help). The terminal output shows the execution of the 'passwd' command. It prompts for the current UNIX password, then asks for a new password and its retype. A confirmation message states 'passwd: all authentication tokens updated successfully.' followed by a new shell prompt.

```
testlogin@localhost:~  
[testlogin@localhost ~]$ passwd  
Changing password for user testlogin.  
Changing password for testlogin.  
(current) UNIX password:  
New password:  
Retype new password:  
passwd: all authentication tokens updated successfully.  
[testlogin@localhost ~]$ _
```

Figure 1.21: Login password change

The prompt will ask for your current password and then it will ask

you to enter your new password twice. If everything went good, the prompt will inform you that your authentication tokens were updated successfully.

An almost identical process applies if you change VNC password, as you can see in Figure 1.22.


A screenshot of a terminal window titled 'initialuser@mulab:~/mulab/modules/current/mulab-core-current/mulabA1'. The terminal shows the command 'vncpasswd' being entered at the prompt '[initialuser@mulab src]\$'. The output shows 'Password:' followed by a blank line, and 'Verify:' followed by a blank line. The prompt then returns to '[initialuser@mulab src]\$ _'.

Figure 1.22: VNC password change

In fact, now you have to type the command `vncpasswd` and, as opposed to `passwd`, it will not ask for your current vnc password but it will simply ask for a new one to set.

1.6.2 Change desktop resolution

Another aspect you most likely want to change is the desktop resolution. It is a really straightforward operation if you already used Gnome desktop environment. If you never did, just follow the screenshot in Figure 1.23.




Figure 1.23: Change desktop resolution

1.7 MPLAB-X[®] issues

There are a few issues that an *MPLAB-X[®]* user must keep in mind, when doing co-simulations with *μLab[®]*.

1.7.1 MPLAB-X IDE[®] project setup

In order to perform a successful co-simulation session, you need to properly set up your *MPLAB-X IDE[®]* project as we will immediately show.

First, your project *must* be compiled with the new toolchains provided by Microchip along with *MPLAB-X IDE[®]*¹ that is, XC8/16/32 compilers.



Warning: if you import an older project that has been developed with MPLAB IDE v8 or previous versions, remember to change the compiler from mpasm or C18/30 one of its new counterpart, otherwise the plugin will misbehave and the co-simulation will not take place.

In addition to the compiler, you also need to choose the right *Hardware Tool* for the project you want to test. In fact, *μLab[®]* needs to query *MPLAB-X IDE[®]* internal simulator about the register and pinout states; therefore, you have to choose the *Simulator* option as current *Hardware Tool*. You can find both compiler and hardware tool options by right clicking the corresponding project listed in the *Project* panel. An example dialog is shown in figure 1.24.

The last detail you need to take care of is setting the right frequency for the simulator.

¹See <http://www.microchip.com/pagehandler/en-us/family/mplabx> , *Compilers* section




Figure 1.24: Project options



Warning: setting the clock frequency in μ Lab[®] will not have any effect on MPLAB-X[®] simulator, so please remember to do it from within MPLAB-X IDE[®].

1.7.2 Error: Cannot start communication server

This error arises for the following three reasons:

- the plugin was not installed, or it was removed because you wanted to upgrade it, but then you forgot to install the newer version;

Solution \Rightarrow contact the administrator

- there is an instance of MPLAB-X IDE[®] already running, and μ Lab[®] cannot connect to it because it has to start MPLAB-X IDE[®] on its own

Solution \Rightarrow save everything you were working in MPLAB-X IDE[®] and close it: μ Lab[®] will start it and take

care of its startup and communication setup

1.7.3 Warning: muLab-MPLABX plugin detected that[...]

When you see a warning message which tells you “*muLab-MPLABX plugin detected that the frequency in the simulator is different from the one set by the Clock Frequency Adapter*”, it means that you are trying to run a simulation but the frequency you set on OSC1/OSC2 is different from the one used from *MPLAB-X IDE*® internal simulation and, therefore, you will get erroneous results. To solve this issue, update the correct oscillator frequency value in the *MPLAB-X*® project, or change the frequency parameter of the AdapterClockFrequency attached to OSC1/OSC2 (see sec. 3.3.2.1).

Chapter 2

Interface Overview

The main *μLab*[®] dashboard is composed of 4 sections:

- the Menu Bar;
- the Toolbar;
- the Main Pane;
- the Status Bar;

and includes a WYSIWYG text editor for writing notes (and examining test reports, see 2.18) during your *μLab*[®] work session.

This chapter explains how to navigate the dashboard and access all of the main *μLab*[®] functionalities; you can find specific details in the corresponding sections.




Figure 2.1: The main μ Lab[®] dashboard

2.1 The menu bar

The menu bar contains several menus used to manage the contents of your machine and your tests.

2.1.1 File menu




Figure 2.2: The File menu

The File menu (figure 2.2) is used to manage your test bench files.

New test bench: create a new, empty test bench. See also 3.1.1 for a detailed walkthrough.

Load test bench: load an existing test bench from a test bench file. See also 3.1.2 for a detailed walkthrough.

Save test bench: save the current test bench to file. This is only active if the test bench has been modified after the last save.

Rename test bench: rename the current test bench. Renaming requires the test bench to be saved (you will be asked for confirm).

About current test bench: show a brief description of the test bench you are currently working on.

Quit: terminate all of the active simulations and debug procedures and exit $\mu Lab^{\text{®}}$.

2.1.2 Machine menu




Figure 2.3: The Machine menu

The Machine menu (figure 2.3) lets the user define the hardware setup of the machine, by creating the components themselves and their interconnections, that model their interactions. The resulting machine can be viewed by selecting the Machine icon from the navigation bar.

New component: create a new component and add it to your machine. See also 3.2.1 for detailed instructions about creating components.

New embedded platform: create a new embedded platform and add it to your machine. See also 3.3.1 for detailed instructions about creating embedded platforms.

New link: setup a connection between two existing items. See also 3.4 for detailed instructions about links.

Edit: edit the properties of the selected item.

Remove: remove the selected item from your machine.

Group: create a group containing the selected items. See also 3.5 for more instructions about groups.

Ungroup: remove the selected group relation between items, without removing the items from the machine. See also 3.5 for more instructions about groups.

2.1.3 Debug procedures menu




Figure 2.4: The Debug Procedures menu

The debug procedures menu (figure 2.4) lets you create, edit and remove debug procedures. For more info about debug procedures, see Chapter 5.

New debug procedure: start the creation of a new debug procedure. See also 5.1.

Edit debug procedure: modify the properties of an existing debug procedure. See also 5.4 for editing individual debug instructions.

Remove debug procedure: delete the selected debug procedure. See also 5.3.

2.1.4 Test sequences menu




Figure 2.5: The Test Sequences menu

The test sequences menu (figure 2.5) lets you create, edit and remove test sequences. For more info about test sequences, see Chapter 6.

New test sequence: start the creation of a new test sequence. See also 6.1.

Edit test sequence: modify the properties of an existing test sequence. See also 6.5 for editing individual tests.

Remove test sequence: delete the selected test sequence. See also 6.3.

2.1.5 Simulation menu




Figure 2.6: The Simulation menu

The Simulation menu (figure 2.6) lets you start numerical simulations on your machine, control the flow of their execution, and access the simulation docs. For more info about simulations, see also Chapter 7.

Start simulation: start the Simulation launch wizard. See also 7.1 for detailed instructions about launching simulations and test sequences.

Pause: pause the current simulation; inactive if no simulations are running. See also 7.2.1.

Resume: resume the current simulation; inactive if no simulations are active and paused. See also 7.2.2.

Cancel: abort the current simulation; inactive if no simulations are active. See also 7.2.3.

Docs: open the workbench notes and test reports managers.

2.1.6 Help menu




Figure 2.7: The Help menu

The Help menu (figure 2.7) lets you access various assistance tools.

Online Help: open the integrated $\mu\text{Lab}^{\text{®}}$ Online Help. **TO DO:** SEE ?? FOR MORE INFO AND SUGGESTIONS ON HOW TO USE IT EFFECTIVELY.

Java system properties: open a viewer that lists the Java properties of your system. Cannot be used to modify their values.

OS environment variables: open a viewer that lists the environment variables of your system. Cannot be used to modify their values.

About: show an informative popup about $\mu\text{Lab}^{\text{®}}$.

2.2 The Tool bar

The Tool bar provides quick shortcuts for the most commonly used functions of the Menu bar. It changes with the view selected in the Navigation Bar, as described in the following sections.

2.3 The Tool bar for the Machine View




Figure 2.8: The Tool bar

Test bench buttons

- new test bench;
- load test bench.

Machine buttons

- new component;
- new embedded platform;
- new link;
- edit item;
- remove item.

Zoom bar

You can use this scroll bar to select the zoom level for the graph. Move the slider to the left to zoom out, and move it to the right to zoom in.

2.4 The Tool bar for the Simulation View

Simulation buttons

- start simulation;
- debug simulation;
- pause current simulation;
- resume current simulation;
- abort current simulation;
- open simulation docs.

2.5 The main pane

Use the Navigation Bar to choose between the Machine view, the Project Dictionaries view, the Debug Procedures view, the Test Sequences view, and the Simulation view for the main pane.

2.5.1 Machine view




Figure 2.9: The Machine view

The Machine view is used to show and edit the machine you're currently working on.

This view is split in two main panes: the left one is used to work on the machine structure, while the right one can be used to set up masks, view and edit variables and parameters of the model, and modify the look of the graph.




Figure 2.10: Machine view, the Graph pane

Graph pane The machine itself is represented by a graph; the nodes of the graph represent the components of the machine, and the arcs of the graph represent the links of the machine.

Component and link properties can be modified through the respective edit dialogs, accessible by double clicking the object you want to edit (or by selecting it and then choosing the `Edit` action from the Machine menu or the toolbar).

Components and links can be deleted through the `Delete` action, which can be selected from the Machine menu, the toolbar, or the context menu (open it by right-clicking on the component). `Del` (on your

keyboard) also works as a generic shortcut for deletion.




Figure 2.11: Machine view, the Info pane

Info pane **TO DO:** TROVARE NOME DECENTE PER LA SEZIONE;

The right section of the machine view consists of the Info pane. It is a panel whose contents depend on the current graph selection. **TO DO:** DA METTERE IN FORMA DI TABELLA

- **No items selected**

Model view: shows machine masks, machine details, parameters (all), variables (all).

- Machine masks: lets you choose and setup machine masks;
- Machine details: ID, name, description of the machine;
- Parameters: a name, value pair list of all of the parameters in the machine components;

- Variables: a name [type], initial value pair list of all of the variables in the machine components.

Graph view: shows graph properties.

- Grid visible: toggle this to show a grid underneath the graph (disabled by default);
- Grid aspect: the way the underlying graph grid is drawn (crosses, dots, lines);
- Grid color: the color of the grid;
- Grid size: the size of the grid elements;
- Background color: the background color of the graph.

- **One component selected**

Model view: shows component details, parameters, variables, plugs and pins.

- Component details: ID, name, description, model file, enabled (if this option is toggled off, the status of the component will not change during simulations **TO DO:** CHE SIGNIFICA?);
- Parameters: a name, value pair list of the component parameters;
- Variables: a name [type], initial value pair list of the component variables;
- Plugs and pins: a list containing the component plugs; each plug is composed of two name [type], initial value pairs describing its pins.

Graph view: shows vertex properties.

- ID: the component ID;
- Font: the font used for the component name in the graph;
- Icon: the icon used to represent the component in the graph;
- Background color: the background color for the component square in the graph;

- Foreground color: the foreground color for the component square in the graph;
- Bounds: the bounds of the component square in the graph;
- Border visible: if toggled on, shows the border of the component square in the graph.

- **One embedded platform selected**

Model view: shows embedded platform details, plugs and pins, processors.

- Embedded platform details: ID, name, description, enabled (if this option is toggled off, the status of the embedded platform will not change during simulations **TC DO** CHE SIGNIFICA?);
- Plugs and pins: a list containing the embedded platform plugs; each plug is composed of two name [type], initial value pairs describing its pins.
- Processors: a list containing the embedded platform microprocessors; each processor entry shows a list containing all of its pins.

Graph view: shows vertex properties.

- ID: the embedded platform ID;
- Font: the font used for the embedded platform name in the graph;
- Icon: the icon used to represent the embedded platform in the graph;
- Background color: the background color for the embedded platform square in the graph;
- Foreground color: the foreground color for the embedded platform square in the graph;
- Bounds: the bounds of the embedded platform square in the graph;

- Border visible: if toggled on, shows the border of the embedded platform square in the graph.

- **One link selected**

Model view: shows link details, connections, wires.

- Link details: ID, name, description, enabled (if this option is toggled off, the status of the link will not change during simulations **TO DO:** CHE SIGNIFICA?);
- Connections: two plug type, name pairs describing (source and target) plugs connected by this link;
- Wire: a list of pin [type], initial value pair couples describing the pins (and the initial values of the variables they carry) connected by the wires of this link.

Graph view: shows edge properties.

- ID: the link ID;
- Font: the font used for the link name in the graph;
- Line style: the line style for this link (bezier, orthogonal, spline);
- Line begin: the style for the beginning of this link line (none, circle, simple, technical, classic, diamond, line, double line);
- Line end: the style for the ending of this link line (none, circle, simple, technical, classic, diamond, line, double line);
- Line color: the color of this link line in the graph;
- Line width: the width of this link line in the graph.

- **More than one item selected**

Model view: no properties to show.

Graph view: no properties to show.

- **Groups**

Nothing happens by clicking on groups.

2.5.2 Project Dictionaries view

The Project Dictionaries view lets you manage the dictionaries of all the relevant project items defined in the current *TestBench*. Each panel, from left to right and from top to bottom, contains the following dictionaries:

- the Dictionary of firmware variables/subroutines, cfr sec. 4.1;
- the Dictionary of processor I/O signals, cfr. sec. 4.2;
- the Dictionary of processor implementations, cfr. sec. 4.3;
- the Dictionary of external data files, cfr. sec. 4.6;
- the Dictionary of runtime firmware subroutines substitutions, cfr. sec. 4.4;
- the Dictionary of firmware implementations, cfr. sec. 4.5;
- the Dictionary of post-process scripts, cfr. sec. 4.7.




Figure 2.12: The Project Dictionaries view




Figure 2.13: The Debug Procedures view

2.5.3 Debug Procedures view

The Debug Procedures view lets you manage the debug procedures for the current test bench.

The list on the left pane displays the available debug procedures: you can click the New Debug Procedure button at the bottom to create a new one, or click an existing one to show the instructions it is composed of, and use the buttons at the bottom to rename or delete it.

The debug instructions editor works in a similar way: click the New Debug Instruction button to add a new debug instruction at the end of the debug procedures, or click an existing one and then use the buttons at the bottom of the pane to edit its contents or delete it.

More info about designing Debug Procedures can be found in Chapter 5 and in the *μLab*[®] Tutorial.

Please note that debug instructions are executed in a sequential order, but every new instruction is added at the bottom of the list: you can use the arrow buttons on the right to change the position of the selected debug instruction.

2.5.4 Test Sequences view




Figure 2.14: The Test Sequences view

The Test Sequences view lets you manage the test sequences for the current test bench.

The list on the left pane displays the available test sequences: you can click the New Test Sequence button at the bottom to create a new one, or click an existing one to show the single tests it is composed of, and use the buttons at the bottom to rename or delete it.

The tests editor works in a similar way: click the New Test button to add a new test at the end of the sequence, or click an existing one and then use the buttons at the bottom of the pane to edit its contents or delete it.

More info about designing Test Sequences can be found in Chapter 6 and in the *μLab*[®] Tutorial.

2.5.5 Simulations view

The Simulations view lets you watch real-time data evolution during the execution of a test sequence.

See Chapter 7 for detailed info about simulation data.




Figure 2.15: The Simulations view

2.6 The status bar

The Status Bar is shown in Figure 2.16 and contains, from left to right, the Log Console, the Status Info, the Memory Usage icon and the name of the current *TestBench*.




Figure 2.16: The Status bar

2.6.1 Log Console




Figure 2.17: The Log console

Clicking the Show Log Console icon opens up a display area for errors, warnings and informative messages regarding the operations being performed in $\mu\text{Lab}^{\text{®}}$. It is possible to copy part of the log console contents into the system clipboard by selecting the text you want to copy, and then pressing ctrl-c or right clicking on the text display area and selecting copy from the context menu. If no text is selected, the entire contents of the log console are copied.

2.6.2 Status Info

Any relevant status messages are shown here.

2.6.3 Memory Usage icon

This bar shows how much memory is being used by the Java Virtual Machine.

Double clicking the Virtual Machine memory usage icon explicitly calls the Java Garbage Collector.

2.7 Notes and Reports

You can open the **Simulation Docs** dialog through the Simulation menu. This dialog lets you access the Notes and Reports panels.

2.7.1 Test Reports

You can specify annotations to be recorded during the execution of any debug instruction through the Debug Instruction Editor. As soon as the simulation is over, $\mu\text{Lab}^{\text{®}}$ saves these lines in a test report: such files can be accessed and managed through the Report Manager.

See sec. 7.6 for more details about Test Reports.




Figure 2.18: The Reports manager

2.7.2 Working Notes

μ Lab[®] features an integrated rich text editor for taking notes within the application.

Working notes belong to the test bench they are saved in: as such, when a test bench folder is moved to another μ Lab[®] installation, its working notes are carried over to the new copy (on the other hand, you can only access a working note from the testbench it belongs to).




Figure 2.19: The Notes manager

The list on the left shows the available notes for the active test bench. Click the New button to create a new note, adding it to the list and opening it in the editor, or double-click an existing list entry (alternatively, select it and press the Load button) to open the corresponding note for editing.

See sec. 7.7 for more details about Test Reports.

Chapter 3

Machine/Process Modelling

3.1 Test bench

A test bench is composed of the machine model, the debug procedures and test sequences, the firmware projects and the python substitutions, the external data files, the post-processing scripts, the working notes and the test reports.

This set of objects is stored in the files inside the test bench directory: *creating (or loading) a test bench* basically means creating (or loading) such a set.

3.1.1 Creating a new test bench

To create a test bench, select `New test bench` from the `File` menu. A pop-up window appears (Figure 3.1) where you will be asked to indicate the name, the author, the image icon and the location on your hard drive of the new test bench you want to create. Once the above information is provided, you can click the `Create` tab and generate the test bench.

Figure 3.1: Fill in the test bench creation form to continue

3.1.2 Loading an existing test bench

To load an existing test bench, select **Load test bench** from the **File** menu, and select the test bench you want to load through the file chooser dialog (test bench directories can be distinguished from their red “ μ ” icon). The selected test bench will be loaded onto the working environ-




Figure 3.2: Select a test bench and press Load to continue

ment.

3.2 Components

3.2.1 Component creation

In order to add a new component to the machine model, select Add component from the Machine menu, or press the button shown in Figure 3.3, to open the Component creation wizard (Figure 3.4). The first



Figure 3.3: Press the New component button to create a new component and add it to the current machine

page of the wizard allows you to specify the name (required) and add a brief description (optional) of the new component; then press Next.




Figure 3.4: Name and description of the new component

3.2.2 Model type

Now, choose an available model type and then press Next. In this release of the software we consider only the *Python* model type.




Figure 3.5: Model type of the new component

3.2.3 Numerical model

The following step of the wizard requires you to formulate the numerical model of the new component.

Once you've decided the model type, you may have to specify some additional settings. This operation is strongly dependent from the model type you selected. For the *Python* model type, cfr. Figure 3.6, click the *New python model* button and choose one of the existing implementation templates, cfr. Figure 3.7.




Figure 3.6: Python component solver setup




Figure 3.7: Python component solver implementation templates chooser

3.2.3.1 Default Python model template

This template is an empty Python model with only the interface with the $\mu\text{Lab}^{\text{®}}$ model. Write the implementation of this model between the code lines

<YOUR CODE (START)>: put here the actual solution of the component model. and

<YOUR CODE (END)> .

When you have done, click the Generate button. At this point, see Figure 3.8, the Python code is ready to be checked (by pressing the Check syntax button), to eventually run its test routine (by pressing the Run module button) if you decided to code it, and to save it in a file named <component name>.py.

If the code verification process, after pressing the Check syntax button, succeeds, you will see the pop-up of Figure 3.9; otherwise, you will see the pop-up of Figure 3.10.

Analogously, if the run of the test routine, after pressing the Run module button, succeeds, you will see the pop-up of Figure 3.11.

3.2.3.2 Constant Gain model template

TO DO: DESCRIPTION ...




Figure 3.8: Python component solver code verification




Figure 3.9: Python component solver code verification success

3.2.3.3 LaTeX model template

Thanks to the *CfL Link*, $\mu\text{Lab}^{\text{®}}$ can generate Python component models from a text written in LaTeX. Supposing you have a file latex with the component model equations written according to the *CfL*[®] standard, this template lets you upload the file latex from the chooser of Figure 3.12. Press the “...” button and choose your latex file, as shown in Figure 3.13 for the file `example_Lorentz.tex`, then press Open. Now click the Generate button. Wait the end of the code generation process,




Figure 3.10: Python component solver code verification failure




Figure 3.11: Python component solver test routine run success

which will produce a success pop-up as in Figure 3.9.

3.2.3.4 Thermometer model template

TO DO: DESCRIPTION ...

3.2.3.5 Voltage Divider model template

TO DO: DESCRIPTION ...




Figure 3.12: LaTeX component solver setup




Figure 3.13: LaTeX component solver file chooser

3.2.3.6 Wave Generator model template

TO DO: DESCRIPTION ...

3.2.4 Parameters and variables

The third step of the wizard lets you set up parameters and variables of your new component.

Within each component, parameters and variables are uniquely identified by their name.

μ Lab[®] lets you use the same name for a parameter and a variable in the same component, or for more than one parameter (or variable) as long as each of them belongs to a different component; however, preserving name uniqueness (when possible) always remains a good practice. You may also add a mnemonic symbol and a brief description.

To complete the setup of a parameter you have to provide its value (defaults to zero) and its unit of measurement (defaults to adimensional). Likewise, to complete the setup of a variable you have to provide its type (Input, Output or State), its initial value (defaults to zero), its unit of measurement (defaults to adimensional) and its resolution, as shown in Figure 3.14. If the component model has been created from a LaTeX




Figure 3.14: Model parameters and variables

file (see sec. 3.2.3.3), also its parameters and variables are automatically created and you will find them in the tables of Figure 3.14.

3.2.5 Pins and plugs

The fourth step of the wizard lets you add plugs to your component.

Click on the New icon to create a new plug, then specify its name and pins: each pin can be associated to an I/O variable (the type of the pin




Figure 3.15: Click the New plug button to create a plug

is the same of the variable); you can add multiple pins to a plug, and multiple plugs to a component.

3.2.6 Post-creation editing

You may also modify the newly added component after the wizard has been completed: to open the editor, either double click the component icon on the graph, or select it and click the Edit item in the Machine menu.

3.3 Embedded Platforms

3.3.1 Embedded Platform creation

To add a new Embedded Platform, select New embedded platform from the Machine menu. This opens up the wizard of Figure 3.16: input the name (required) and a brief description (optional) of the new embedded platform, then press Next to continue.




Figure 3.16: Select New Embedded Platform to create a new Embedded Platform and add it to the current machine




Figure 3.17: Setup the pinout of the embedded platform

3.3.2 Pinout

The pinout configuration lets the user to create, modify or delete the items of the *Dictionary of processor I/O signals* (for brevity, “pin alias”) and to setup the adapters for these items.

The **Name** column displays the name of the pin alias. The value on the **Signal** column shows the name of the model variable connected to each pin by a link (it's empty if the pin isn't connected to

any components).

The Adapter column lets you specify (and then configure) adapters for each pin alias: click on the description of the adapter (it's empty if no adapters have been configured for that pin alias) to edit it. Each adapter type is described in the following subsections.

3.3.2.1 Clock frequency

Here the user can set the external clock frequency input to the microcontroller. The adapter accepts one parameter `Clock frequency [Hz]` and no connections are required to the pin of the embedded platform model (eventual data fed up to the pin are not considered).

3.3.2.2 Input voltage

Here the user can set a constant input voltage, with no need to build an external component in the $\mu\text{Lab}^{\text{®}}$ model. The adapter accepts one parameter `Constant voltage [V]` and no connections are required to the pin of the embedded platform model (eventual data fed up to the pin are not considered).

3.3.2.3 Input/Output frequency-modulated pulse train

Here the user can generate/read a high frequency-modulated pulse train at microcontroller pins, without the need to sample the $\mu\text{Lab}^{\text{®}}$ model at the Nyquist frequency of the signal or higher. The adapter accepts one parameter `Duty cycle [%]` and reads/writes the value at the embedded platform pin as the frequency of the pulse train.

3.3.2.4 Input/Output width-modulated pulse train

Here the user can generate/read a high frequency width-modulated pulse train at microcontroller pins, without the need to sample the $\mu\text{Lab}^{\text{®}}$ model at the Nyquist frequency of the signal or higher. The adapter accepts one parameter `Frequency [Hz]` and reads/writes the value at the embedded platform pin as the duty cycle of the pulse train.

3.3.2.5 Input/Output bit stream

Here the user can generate/read a serial bit stream at microcontroller pins, without the need to sample the $\mu\text{Lab}^{\text{®}}$ model at the Nyquist frequency of the signal or higher. The adapter accepts two parameters, Baud rate and Message length and reads/writes the values at the embedded platform pin as the bit stream.

3.3.2.6 Device pin

TO DO: ...

3.3.3 Plugs

The final step of the wizard lets you add plugs to your embedded platform.

Click on the New icon to create a new plug, then specify its name and pins: each pin can be associated to an I/O variable (the type of the pin is the same of the variable); you can add multiple pins to a plug, and multiple plugs to an embedded platform. After all the plugs have been created, press Ok to end the embedded platform creation wizard.

3.3.4 Post-creation editing

You may also modify the newly added embedded platform after the wizard has been completed: to open the editor, either double click the embedded platform icon on the graph, or select it and click the Edit item in the Machine menu.

3.4 Links

In order to create a working machine, its components must be linked to each other; you can do this by creating links from the Machine menu (Machine → New link) or with the button shown in Figure 3.19.




Figure 3.18: Plug configuration dialog: specify the name of the plug and the pins it's composed of.



Figure 3.19: Select New link to start the link creation wizard

Doing so brings up the link creation wizard (Figure 3.20). Input the name (required) and a brief description (optional) of the new link, then press Next to continue.

Connections between two components of any machine are formed by linking one plug on each machine with each other, as shown in Figure 3.21.

Such a connection can only be made if the two plugs are compatible. Compatibility between plugs is verified by checking if all of the pins on the first plug can be correctly connected with all of the pins on the second plug.

Two pins can be connected with each other if their I/O types are compatible (i.e. if the first is an input pin and the second is an output pin or vice versa, or if one is a micropin) and if their units of measure-




Figure 3.20: The link creation wizard:specify the name of the new link; you may add a description text (optional). When you are done, press Next to continue.




Figure 3.21: Select source and target plugs of the new link.

ment are the same. Note that the connection begins at the output pin and ends at the input pin.

Different numbers of pins, or failure to match one or more pins on one plug, will cause the two plugs to be incompatible, therefore unavailable for being connected with each other.




Figure 3.22: The selected plugs are compatible: drag the output/microp pins to the input/microp pins to create wires. Press **Finish** when done.




Figure 3.23: The selected plugs are not compatible for connection

3.5 Groups

Selecting multiple components (by either clicking them one by one while pressing **ctrl** or **shift**, or by doing a rectangle selection) enables the group

command on the toolbar

404
Image not
found!


Figure 3.24: Drag a box around the components you want to group. You may now press the Group button to group them

Upon creating a group, you'll be asked for a group name (cannot be blank).

404
Image not
found!

Figure 3.25: Specify the name of the new group and press OK to create it


A group can be either collapsed (only the group icon and name are shown on the graph, its contents hidden) or expanded (no group icon and name, all of its contents are shown): you can switch between the two display modes by clicking on the expand/collapse button on the top left corner. It's possible to change the contents of a group without destroying and recreating it: expand it, and drag the component you want to add (or remove, respectively) inside (or outside) the group box. If you want to remove a group, select it and press the ungroup button. Note that this only deletes the group view, not the components themselves.



404
Image not
found!

404
Image not
found!

Figure 3.26: Collapsed and expanded views of a group. Press + to switch between the two modes



404
Image not
found!

404
Image not
found!

Figure 3.27: Components being added to (left picture) and removed from (right picture) a group through drag-and-drop



404
Image not
found!

Figure 3.28: Ungrouping removes the old group relationship between objects, but the components themselves are not deleted

Chapter 4

Project Dictionaries Design

4.1 Dictionary of firmware variables/subroutines

In order to create, modify or delete an alias of a firmware variable/subroutine, use the panel and the buttons indicated in Figure 4.1.




Figure 4.1: Here it is the list of firmware variable/subroutine aliases; at the left bottom there are four buttons to create a variable ("blue star"), create a subroutine ("yellow star"), modify the selected variable/subroutine ("pencil"), delete the selected variable/subroutine ("thrash"); then, press OK to actuate the selected action or cancel to abandon it.

4.2 Dictionary of processor I/O signals

In order to create, modify or delete an alias of a processor I/O signal (for brevity, "pin alias"), see sec. 3.3.2.

4.3 Dictionary of processor implementations

In order to create, modify or delete a processor implementation, use the panel and the buttons indicated in Figure 4.2. The editor is shown in Figure 4.3.




Figure 4.2: Here it is the list of processor implementations existing in the project; at the left bottom there are three buttons to create, modify or delete the selected implementation.





Figure 4.3: The editor of a processor implementation: the user should specify a *name*, and the bindings with the *simulator*, the specific *device* inside the simulator and the alias-physical pins association.

4.4 Dictionary of runtime firmware subroutines substitutions

The dictionary of runtime firmware subroutines substitutions (see an example in Figure 4.4), is located in the left bottom of the *Project Dictionaries View* (sec. 2.5.2).



Firmware subroutine alias	Arguments: Fw variables and pins alias, model params	Python module	Python function
python_adc	ADC1BUF0 ADC1BUF2 ADC1BUF3 SpeedDemand pos V_ia V_...	adc.py	updateADCBUF
control_algo	Beta omega PWM1H PWM2H PWM3H V_ia V_... SpeedDem...	control_algo.py	main
control_algo	PWM1H PWM2L PWM3H PWM2L PWM3H PWM2L omega the...	control_algo_co...	main
control_algo	V_ia V_... Beta omega PWM1H PWM2H PWM3H run/stop B...	control_algo_co...	main
control_algo	V_ia V_... PWM1H PWM2H PWM3H run/stop-button SpeedD...	control_algo_co...	main
		C:\open.Simulink\...	

Figure 4.4: An example of a dictionary of runtime firmware subroutines substitutions

In order to:

- create a new substitution, press the leftmost button (a new item appears, as a blue table row), then click on the cells from the left to choose:
 - the alias of the firmware function to be substituted, see Fig. 4.5;
 - the arguments that could be passed to this firmware subroutine (Fig. 4.6); possible arguments are: items of the *Dictionary of firmware variables* (sec. 4.1), items of the *Dictionary of the processors I/O signals* and *model parameters* (sec. 3.2.4);
 - the python module containing the function that substitutes the firmware subroutine (4.7) and the python function itself (by writing its name in the text field).

- create a substitution from a LaTeX file, press the second button from left, and then submit the file selected through a standard file chooser;
- edit the python module, select a substitution (table row) and press the third button from the left;
- delete a substitution, press the the rightmost button (thrash icon).




Figure 4.5: Select the alias of the firmware function to be substituted, and press Choose to confirm the selection or cancel to discard it.




Figure 4.6: Choose the arguments by typing them (Ctrl+Space does the auto-completion) and press the circle buttons to add or delete an argument from the list; press OK to confirm the selection list or cancel to discard it.




Figure 4.7: Select the python file with the standard chooser of the OS.

4.5 Dictionary of firmware implementations

In order to create, modify or delete a firmware implementation, use the panel and the buttons indicated in Figure 4.8. The editor of a firmware implementation is shown in Figure 4.9 and the editor of a firmware variable/subroutine binding is shown in Figure 4.10.




Figure 4.8: Here it is the list of firmware implementations existing in the project; at the left bottom there are three buttons to create, modify or delete the selected implementation.

4.6 Dictionary of external data files

In order to create, modify or delete a reference to an external datafile, use the panel and the buttons indicated in Figure 4.11. The editor is shown in Figure 4.14.

4.7 Dictionary of post-process scripts

In order to create, modify or delete a postprocessing script, use the panel and the buttons indicated in Figure 4.13. The editor is shown in Figure 4.14.




Figure 4.9: The editor of a firmware implementation: the user should specify a *name*, the *project dir*, he must press the *Load firmware symbols* button, choose the compiler and the processor implementation and the bindings with the *variables* and the *subroutines* implemented in the firmware project and corresponding to the dictionary items.




Figure 4.10: The editor of a firmware variable/subroutine binding: the user double click the alias of a variable/subroutine and the editor open up. He then must choose the *Name* of the variable corresponding to the selected alias, among the symbols defined in the firmware project and presented in a popup list of the editor; he must also specify the *Type* of the variable/subroutine-return-value and, if the variable is a C struct/vector, the offset **in bytes** at which the desired scalar value is allocated.




Figure 4.11: Here it is the list of references to external datafiles considered in the project; at the left bottom there are three buttons to create, modify or delete the selected implementation.




Figure 4.12: The editor of a reference to an external datafile: the user should specify a *name*, the datafiles involved in this reference (usually there is a single datafile), and the bindings of each column of data with the corresponding project item, that can be: items of the *Dictionary of firmware variables* (sec. 4.1), items of the *Dictionary of the processors I/O signals and model parameters and variables* (sec. 3.2.4).



Figure 4.13: Here it is the list of the postprocessing scripts existing in the project; at the left bottom there are three buttons to create, modify or delete the selected implementation.




Figure 4.14: The editor of a postprocessing script: the user should specify a *name*, the python file containing the postprocessing script, and write the python code of the script.

Chapter 5

Debug Procedures Design

Use the navigation bar from the main *μLab*[®] dashboard to access the *Debug Procedures View* (sec. 2.5.3): it allows the user to design the Debug Procedures to be used in the project. Its structure is shown in Figure 5.1:

5.1 Creating a Debug Procedure

From the Debug Procedures page, click the `Create new debug procedure` button; then input the name of the new debug procedure and press `OK` to continue.

5.2 Renaming a Debug Procedure

To rename a debug procedure, select it from the list and click the `Edit procedure` button.




Figure 5.1: The *Debug Procedures View*: there are two vertical sections, that show the list of the existing Debug Procedures (left) and the list of the Debug Instructions (right) existing in the selected Debug Procedure.

5.3 Deleting a Debug Procedure

To delete a debug procedure, select it and click the **Remove procedure** button.




Figure 5.2: Input a name for the new Debug Procedure and press OK to continue

5.4 Creating/Editing/Deleting a Debug Instruction

Click the **Create new Debug Instruction** button to start the creation of a new Debug Instruction that will be added at the bottom of the instructions list of the current Debug Procedure. To edit a debug instruction, select it from the list and press the **Edit instruction** button. To remove a debug instruction from the debug procedure, select it from the list and press the **Remove instruction** button. To change the position of a Debug Instruction inside a Debug Procedure, use the arrow buttons as shown in Figure 5.6. The Debug Instruction editor is shown in Figure 5.5.

Configure the new Debug Instruction through the Debug Instruction Editor (refer to the *μLab*[®] tutorial for detailed information on how




Figure 5.3: Select a Debug Procedure and click Edit Procedure to rename it

to configure debug instructions).




Figure 5.4: Select a Debug Procedure and click Remove Procedure to remove it from the list

5.5 Rearranging the Debug Instruction list

You can use the up and down buttons to move up or down (by one step) a debug instruction.

Debug instruction fulfilling their activation and execution conditions will be performed in this order.




Figure 5.5: Click Create new Debug Instruction to add a new Debug Instruction



Figure 5.6: Click the arrow buttons to move a Debug Instruction up or down the list

Chapter 6

Test Sequences Design

Use the navigation bar from the main *μLab*[®] dashboard to access the *Test Sequences View* (sec. 2.5.4): it allows the user to create and delete Test Sequences, and edit their contents. Its structure is shown in Figure 6.1:

6.1 Creating a new Test Sequence

From the Test Sequences page, click the `Create new test sequence` button; input the name of the new test sequence and press `OK` to continue.

6.2 Renaming a Test Sequence

To rename a test sequence, select it from the list and click the `Edit test sequence` button.




Figure 6.1: The *Test Sequences View*: there are two vertical sections, that show the list of the existing Test Sequences (left) and the list of the Tests (right) defined in the selected Test Sequence.

6.3 Deleting a test sequence

To delete a test sequence, select it and click the `Remove test sequence` button.

6.4 Copy/Paste a test sequence

To copy/paste a test sequence, select it and click first the `Copy test sequence` button; then select the position to paste a copy of the Test Sequence and click the `Paste test sequence` button (Figure 6.5).




Figure 6.2: Input a name for the new Test Sequence and press OK to continue.

6.5 Creating/Editing/Deleting a new Test

Click the **Create new Test** button to start the creation of a new Test that will be added at the bottom of the current Test Sequence. To edit a test, select it from the list and press the **Edit test** button. To remove a test from the test sequence, select it from the list and press the **Remove test** button. The Test editor has multiple tabs:

- *Details*, is shown in Figure 6.6;
- *Details*, is shown in Figure 6.7;
- *Details*, is shown in Figure 6.8;
- *Details*, is shown in Figure 6.9;
- *Details*, is shown in Figure 6.10;

6.6 Rearranging the Test list

You can use the up and down buttons to move up or down (by one step) a test (Figure 6.11).




Figure 6.3: Select a Test Sequence and click Edit test sequence to rename it.

When a test sequence is started with the Launch all tests option active, tests are performed in the same order they are found in the sequence, even though they are independent (i.e. machine states don't carry over between subsequent tests).




Figure 6.4: Select a Test Sequence and click Remove test sequence to delete it.




Figure 6.5: Select a Test Sequence and click Copy test sequence and Paste test sequence (rightmost buttons).




Figure 6.6: Click.




Figure 6.7: Click.




Figure 6.8: Click Create new Test to add a new Test in the Test Sequence.




Figure 6.9: Click Create new Test to add a new Test in the Test Sequence.




Figure 6.10: Click Create new Test to add a new Test in the Test Sequence.




Figure 6.11: Click the arrow buttons to move a Test up or down the list

Co-Simulations run

Use the navigation bar from the main μLab^{\circledR} dashboard to access the *Simulation View* (sec. 2.5.5): it allows the user to monitor the running Tests interactively, and to do some post-processing. Its structure is populated only when there is at least one Test running or finished, and it is shown in Figure 7.1:




Figure 7.1: The *Test Simulation View*:

7.1 Starting Simulation

In order to launch a Simulation, you have to perform a few basic steps, described in the following subsections.

7.1.1 Test selection

There are two ways to select a Test or a Test Sequence:

- From any view in $\mu\text{Lab}^{\text{®}}$: click the *Launch Test* or the *Launch Test Sequence* buttons (Figure 7.2) to show the Test Sequence selection screen (Figure 7.3). Note that pressing the *Launch Test Sequence* button causes all of the contained Tests to be run one after another, sequentially. Moreover, every test is unrelated from the others (i.e. machine states don't carry over between two consecutive tests).




Figure 7.2: The *Launch Test* (left) and the *Launch Test Sequence* (right) buttons.

- From the *Test Sequences View*: if a Test Sequence and eventually also a Test are selected in this view, click the *Launch Test* or the *Launch Test Sequence* buttons; the selection made will bypass the Test Sequence selection screen (Figure 7.3) and bypass also the Test selection screen (Figure 7.4), if also a Test is selected in this view or the *Launch Test Sequence* button has been pressed.




Figure 7.3: Choose a test sequence from the list and click Next




Figure 7.4: Select the test you want to execute and click Next

7.1.2 Machine configuration

Machine variables and parameters are displayed in a tree-structured table, grouped by component (and by processor model in case they belong to an embedded platform); any values specified here will override both the starting default values (only for the execution of the selected

Test or Test Sequence) and the values in the specific Test configurations.




Figure 7.5: Configure the starting values of variables and parameters

7.1.3 Links configuration

Each link between model components can be here enabled or disabled; any values specified here will override both the starting default values (only for the execution of the selected Test or Test Sequence) and the values in the specific Test configurations.




Figure 7.6: Configure the starting values of variables and parameters

7.1.4 Debug components

Select which components you want to debug during the execution of the simulation (select multiple components by pressing CTRL while clicking them). Note that only the components that support debugging will be available for selection.




Figure 7.7: Select the components you want to debug by clicking them while pressing CTRL.




Figure 7.8: Select the components you want to debug by clicking them while pressing CTRL.

7.2 Simulation flow

The simulation flow can be controlled with the buttons shown in Figure 7.2.



Figure 7.9: The flow control buttons, from left to right: Pause, Resume and Cancel

7.2.1 Pausing Simulations

Use this command to pause the execution of the Test shown in the active tab.

7.2.2 Resuming Simulations

Use this command to resume the execution of the Test shown in the active tab.

This action can only be performed if the Test was previously paused: an aborted Test cannot be resumed.

7.2.3 Aborting Simulations

Use this command to stop and abort the execution of the current Test. Aborting a Test also cancels the creation of its Test Reports.

7.3 Data visualization

7.3.1 Data view




Figure 7.10: The data view is composed of two main sections: on the left, the data tables; on the right, the selection panes

Select from the menu on the right the data you want to watch by clicking them; hold CTRL while clicking to select multiple items.

The Data view shows the last value taken by the selected items; specifying an instant in the text field on the right lets you see the values taken by the variables at that time.

This feature is only available in the data view, and can only be used to show values at one given instant, not during an interval.

The Data view also supports Simulation Masks: analogue to Machine Masks, they can be used to filter the values shown in the tables, which is especially useful when dealing with complex models described by large quantities of data.

7.3.2 Chart view

The chart view gives you a real-time graphical representation of the model variables and parameters, updated instant by instant while the *Test* is being executed. The timeline starts at the beginning of the simulation,




Figure 7.11: The Chart view

and goes all the way to the current instant: you can zoom on a specific region by indicating it with the mouse pointer, and scrolling with the wheel (scroll up to zoom in, scroll down to zoom out).

Note that the minimum zoom level is the original one; click on the graph to automatically reset the zoom.

You can select the variables you want to be shown in a graph by clicking on their names in the selection panel: press ctrl while clicking for multiple selection.

Two display modes for data series are supported: one with a common y-axis, when viewing comparable data, and one with separate y-axes, when the data you're viewing cannot be compared (i.e. because of different units of measurement or different orders of magnitude). If you want to save or print a graph, right-click the graph area and select Save




Figure 7.12: Common and separate y-axis modes buttons

or Print from the context menu.

7.3.3 Animation view

This functionality is forthcoming.

This view lets you use the simulation data as input variables for a graphical animation. Custom animations can be added to the built-in set: write the Java FX script that implements your animation, opportunistically binding its variables to the simulation parameters, and place the script file in the test bench folder.

7.3.4 Debug view

The debug view lets you modify breakpoints and watch variables, parameters and memories while the simulation is running. Click on a line




Figure 7.13: The Debug view

number/instruction address to add a breakpoint on that line; click again to remove it. When the execution of the platform firmware or component solver stops at a breakpoint (Figure 7.14), you can use the control buttons to either skip that breakpoint, do one step (that is, execute the current instruction and stop at the next one), or continue the simulation (until the following breakpoint is reached), see Figure 7.15.

Click the **Memories** button to show a watch table for variables data (Figure 7.16).




Figure 7.14: Active breakpoints in the embedded firmware co-simulation




Figure 7.15: Debug control buttons




Figure 7.16: Click the Memories button to watch variables

7.4 Co-simulation logs

TO DO: ...

7.5 Post Processing

TO DO: ...




Figure 7.17: The Post Processing simulation view:

7.6 Test Reports

Test Reports are automatically created during the execution of Simulations.

Open the Simulation Docs window and click the Test Reports tab to access the Reports Manager.




Figure 7.18: Docs simulation view: the Test Reports tab

7.6.1 Reports Manager

The layout of the Reports Manager is composed of two parts:

- on the left, the list of the Test Reports stored in the active test-bench;
- on the right, the Test Report editor.

Reports can be opened in the editor by double-clicking their name on the list;

groups instead can be expanded or collapsed by double-clicking them.

Right-clicking the tab of a Report in the editor shows a pop-up menu you can use to close that report, close all of the other reports, or close all of the open reports.

Select a Report on the list and click the **Delete** button to delete the selected Report.

Click the **Search Reports** button to open the advanced search tools window.

7.6.2 Text search tools

The *μLab*[®] Reports Manager provides you with two text search tools.

You may search for a string in the currently active Report by using the **Search text** field at the bottom of the Report panel. Any text matching the specified string will be then highlighted in the active Report, and the editor will scroll to show the first match instance.

If you need to search for a string in all of the Reports stored in the active testbench, without opening every single one of them in the editor, open the advanced search tools window by clicking the **Search Reports** button.

Specify the string you want to search in the **Search text** field, select one of the two result display modes, and click **Ok** to perform the search:

- **search reports and show list** looks for matches with the specified string and displays a list of the Reports containing any matches; you may then pick which Reports to open by selecting them on the list (press **CTRL** while clicking them for multiple selections) and clicking **Choose**;
- **search reports and open them** looks for matches with the specified string and automatically open all of the Reports containing

any matches.

7.6.3 Report Groups management

Report Groups are created by default when you execute a whole Test Sequence; a Report generated by the execution of a single Test (that is, by using the `Launch just 1 test in the sequence` setting), by default, does not belong to any Report Groups.

Double click on a Group to expand or collapse it: expanding a Group shows a list of the Reports it contains.

Select a set of Reports (press CTRL while clicking the single Reports for multiple selection) and click the `Create` button to create a new group containing the selected Reports;
select an existing group and click `Rename` to rename it;
select an existing group and click `Dissolve` to remove the Group only: the Reports it contained will become single Reports;
select an existing group and click `Delete` to remove the Group and delete the Reports it contains.

7.7 Working Notes

Working Notes are automatically created during the execution of Simulations.

Open the Simulation Docs window and click the Working Notes tab.




Figure 7.19: Docs simulation view: the Working Notes tab